



Installation Help Document


Digital Signature Component (DSC)

Download EXE File as per your system Configuration:


- **32BIT:** <https://dsc.mponline.gov.in/setup/32X.rar>
- **64BIT:** <https://dsc.mponline.gov.in/setup/64X.rar>

Steps to install the setup.


- Click on nCodePKIComponent setup, popup will be shown as below.




- Click on next, Agree on terms and condition.



- Click on finish.



- After you click the finish button Applet-less PKI component will run automatically and you will get icon in the system try




Steps to uninstall / re-install


- Go to **control panel >> add / remove program >>** search for **nCodePKIComponent V4.0**
- Right-click on **nCodePKIComponent V4.0** and
- Select **uninstall / change** which will open a wizard
- Follow wizard to uninstall **nCodePKIComponent V4.0**
- Right-click on **Remove_OLD_Settings.bat** (which you have already downloaded with the installer) and **run as administrator** to remove configuration if any remain.
- Install **nCodePKIComponent V4.0** using the setup to use it once again

Import security certificate (if you are not able to use applet less PKI component)


- Close all browsers open in the system.
- Save **localhost.crt** in the system which is shared with this help document.
- Click **WIN + R** (to open the run command), after the dialog box is open
 - Write **certmgr.msc** in run command and press enter or click on the OK button




- It will open a new dialogue box as shown below
- After getting below the dialog box




- Go to “Trusted Root Certification” >> “Certificates”




- Right Click on “Certificates” go to >> “All Tasks” > “Import...”
 - It will open the wizard as shown




- Follow Certificate import wizard to import “**localhost.crt**” file in your “**Trusted Root Certification authority**”




- Click **Next** to continue



- Select “**localhost.crt**” file and click **Next**




- Click **Next** to continue




- Then click on Finish

- You will get one more dialog box as show below
 - Click on **Yes**



- After that you will get message **"The import was successful"**



- Close all open windows

- Open Chrome web browser
 - Try to access the following URL <https://localhost:13591/>
 - If you are getting the following message changes are applied successfully.

